

Common workflow

Puffin allows you to write 3 types of files

- Integrated
- Field mesh
- Electron macroparticles

All 3 types include VizSchema metadata so that they can be used in e.g. VisIt. Due to how the data is stored in Puffin, the field mesh files in both 1D and 3D cases are stored in Fortran ordering, and have to be rearranged into C ordering to work in VisIt. This can be done by using the `ReorderColMajorFtoColMinorC.py` script.

The use cases in the 1D and 3D modes are quite different - in 1D the data dumps are very small, and so you can write the full data dumps often - say, every undulator period. In contrast, the 3D data dumps can be huge, so you probably want to avoid doing a lot if you can, but it may be unavoidable for your situation depending on what you want to see! In the 3D case usually only a few full full dumps will typically be made through the run, and the integrated data is dumped more often - again, perhaps at every undulator period.

1D Case

- 1D case
 - Run Puffin
 - Typically use frequent dumps of field and macroparticle data
 - Run the `convert2C` script on the `aperp` files
 - Run `powPrep` if desired
 - Py plotting routines can be used on the mesh and macroparticle dumps

For 1D mode, the data sizes are small enough so that dumps can be done frequently on modern machines. Runs may typically be done locally, or they may be moved from remote locations due to relatively small file size, removing the need for remote visualization software.

In the 3D case, the integrated data is automatically high-pass filtered (due to the diffraction algorithm) so that the integrated data immediately looks familiar to a FEL physicist. The 1D case is NOT filtered in the simulation, so the integrated data files include the low-frequency emission, and this obscures the FEL gain in the data until typically around halfway to saturation.

Because of this, usually many mesh and electron data dumps are used in 1D mode, and Puffin comes with a few Python scripts to analyse the data from the 'raw' dumps. The integrated data is often not used so much in this use case.

This allows one to choose, for example, to measure the gain at a certain radiation frequency quickly and easily from the 1D files. If only the integrated data were used, this information would be lost.

1D run example workflow

Run Puffin:

```
mpirun -np 2 puffin f2main.in
```

Reorder the field mesh files from Fortran to C ordering:

```
for i in $(ls f2main_aperp_*.h5); do python  
$PUFFDIR/bin/post/ReorderColMajorFtoColMinorC.py $i; done
```

The python scripts can plot field spectrum, filtered 1D power, etc from the *aperp_C* files:

```
python $PUFFDIR/bin/pyPlotting/plotFiltPow.py f2main_aperp_C_6900.h5  
python $PUFFDIR/bin/pyPlotting/plotSpecPow.py f2main_aperp_C_6900.h5
```

and so forth. The filtered energy can be plotted by supplying the 'basename', and the script automatically detects and uses all the relevant files according to the naming convention above (basename + aperp_C_step.h5):

```
python $PUFFDIR/bin/pyPlotting/plotFiltEn.py f2main
```

Visit can be used to view the bunching, current, etc from the integrated files. Python scripts to plot these, similar to the field plotting routines above, will be added soon.

3D Case

- 3D case
 - Run Puffin
 - Typically use infrequent dumps of field mesh and electron macroparticles, but frequent integrated writes
 - Run the reduce script on the aperp files
 - Run the convert2C script on the reduced aperp files
 - Run the powPrep script on the integrated data files
 - Py plotting routines and Visit can be used on these processed files

Typically you'll use less data dumps for the run as in 1D, as the files are huge. For CLARA, a single 3D field mesh file is around 350GB, and to write enough to get a nice gain curve from this can easily then take up multiple 10's or 100's of TB's per run.

This poses interesting problems from the data reduction point of view. Ultimately, the more data dumps, the better, but Puffin currently outputs enough integrated data (power and so on) so that you can see if the FEL is working. The diffraction algorithm in Puffin includes a high-pass filter, so most of the low frequency CSE effects in the power curves should not be there (the filter may be adjusted in the Puffin input file, and you could conceivably get the low frequency content back into the run if you wanted). So the radiated energy curves as output in the integrated files look fine without having to worry about low frequencies, as opposed to the 1D case.

If you are interested in the power growth at 2 or more distinct frequencies, then the energy (gain) curve will include all of these frequencies, and they cannot be retrieved from the integrated data. For now, many dumps should be written out if you really want to get into the detail of how these separate colours evolve through the undulator. There may be options added in the future to make Puffin filter some field energy/power output for you, but this may be computationally unfeasible for a few different reasons.

More likely, Puffin will have an option to write out a reduced mesh, and allow the selection of an inner mesh for writing, where the inner, say 30x30 nodes in the transverse mesh are dumped. This dramatically reduces the mesh size in the files.

3D run example workflow

Run Puffin:

```
mpirun -np 2 puffin f1main.in
```

'Reduce' the field mesh files to the center nodes in the transverse plane:

```
for i in $(ls f2main_aperp_*.h5); do python $PUFFDIR/bin/post/reduceField.py $i; done
```

Reorder the field mesh files from Fortran to C ordering:

```
for i in $(ls f2main_aperp_small_*.h5); do python  
$PUFFDIR/bin/post/ReorderColMajorFtoColMinorC.py $i; done
```

The python scripts can plot field spectrum, filtered 1D power, etc from the *aperp_C* files:

```
python $PUFFDIR/bin/pyPlotting/plotFiltPow.py f2main_aperp_C_6900.h5  
python $PUFFDIR/bin/pyPlotting/plotSpecPow.py f2main_aperp_C_6900.h5
```

and so forth. The filtered energy can be plotted by supplying the 'basename', and the script automatically detects and uses all the relevant files according to the naming convention above (basename + aperp_C_step.h5):

```
python $PUFFDIR/bin/pyPlotting/plotFiltEn.py f2main
```